

FIT FILE TYPES

Description

Copyright Information and Usage Notice

This information disclosed herein is the exclusive property of Dynastream Innovations Inc. The recipient and user of this document must be an ANT+ Adopter pursuant to the ANT+ Adopter's Agreement and must use the information in this document according to the terms and conditions of the Adopter's Agreement and the following:

- a) You agree that any products or applications that you create using the ANT+ Documents and ANT+ Design Tools will comply with the minimum requirements for interoperability as defined in the ANT+ Documents and will not deviate from the standards described therein.
- b) You agree not to modify in any way the ANT+ Documents provided to you under this Agreement.
- c) You agree not to distribute, transfer, or provide any part of the ANT+ Documents or ANT+ Design Tools to any person or entity other than employees of your organization with a need to know.
- d) You agree to not claim any intellectual property rights or other rights in or to the ANT+ Documents, ANT+ Design Tools, or any other associated documentation and source code provided to you under this Agreement. Dynastream retains all right, title and interest in and to the ANT+ Documents, ANT+ Design Tools, associated documentation, and source code and you are not granted any rights in or to any of the foregoing except as expressly set forth in this Agreement.
- e) DYNASTREAM MAKES NO CONDITIONS, WARRANTIES OR REPRESENTATIONS ABOUT THE SUITABILITY, RELIABILITY, USABILITY, SECURITY, QUALITY, CAPACITY, PERFORMANCE, AVAILABILITY, TIMELINESS OR ACCURACY OF THE ANT+ DOCUMENTS, ANT+ DESIGN TOOLS OR ANY OTHER PRODUCTS OR SERVICES SUPPLIED UNDER THIS AGREEMENT OR THE NETWORKS OF THIRD PARTIES. DYNASTREAM EXPRESSLY DISCLAIMS ALL CONDITIONS, WARRANTIES AND REPRESENTATIONS, EXPRESS, IMPLIED OR STATUTORY INCLUDING, BUT NOT LIMITED TO, IMPLIED CONDITIONS OR WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, DURABILITY, TITLE AND NON-INFRINGEMENT, WHETHER ARISING BY USAGE OF TRADE, COURSE OF DEALING, COURSE OF PERFORMANCE OR OTHERWISE.
- f) You agree to indemnify and hold harmless Dynastream for claims, whether arising in tort or contract, against Dynastream, including legal fees, expenses, settlement amounts, and costs, arising out of the application, use or sale of your designs and/or products that use ANT, ANT+, ANT+ Documents, ANT+ Design Tools, or any other products or services supplied under this Agreement.

If you are not an ANT+ Adopter, please visit our website at www.thisisant.com to become an ANT+ Adopter. Otherwise you must destroy this document immediately and have no right to use this document or any information included in this document.

The information contained in this document is subject to change without notice and should not be construed as a commitment by Dynastream Innovations Inc.

Products sold by DYNASTREAM are not designed for use in life support and/or safety equipment where malfunction of the Product can reasonably be expected to result in injury or death. Your use or sell such products for use in life support and/or safety applications at your own risk and agree to defend, indemnify and hold harmless DYNASTREAM from any and all damages, claims, suits or expense resulting from such use.

©2012 Dynastream Innovations Inc. All Rights Reserved.

Revision History

Revision	Effective Date	Description
1.0	May 2010	Initial release
1.1	February 2010	Added File Types: Device, Course, Sport Settings, Goals and Totals Added Sections: Bike and SDM profiles (Settings File)
1.2	November 2011	Fixed error in Sport File description Added appendix with HRV description
1.3	January 2012	Added Schedule, Activity Summary, Monitoring and Daily Monitoring File Added further description to Activity File
1.4	April 2012	Moved hrv data description to Activity File description. Described activity file messages in more detail.

Table of Contents

1	Overview of the FIT File Protocol	8
2	Related Documents.....	8
3	Device File.....	9
3.1	FIT Messages	10
3.1.1	software Message	11
3.1.2	capabilities Message.....	11
3.1.3	file_capabilities Message.....	11
3.1.4	mesg_capabilities Message	11
3.1.5	field_capabilities Message	11
3.2	Device File Example.....	12
4	Settings File	14
4.1	FIT Messages	15
5	Sport Settings File.....	16
5.1	FIT Messages	17
5.1.1	zones_target Message	17
5.1.2	sport Message.....	18
5.1.3	hr_zone Message	18
5.1.4	power_zone Message	18
5.1.5	met_zone Message.....	18
5.2	Sport File Example.....	18
6	Blood Pressure File.....	20
6.1	FIT Messages	20
6.2	BP File Examples	23
7	Weight File.....	27
7.1	FIT Messages	28
7.2	Weight File Examples.....	30
8	Workout File	33
8.1	FIT Messages	34
8.2	Workout Message	36
8.3	Workout_steps Message	36
8.3.1	Duration_type Dynamic Fields.....	37
8.3.2	Target_type Dynamic Fields.....	37
8.3.3	Target values vs Custom target values	37
8.3.4	Workout Intensity	38
8.3.5	Setting Power and Heart Rate Values	38
8.4	Workout File Examples	39
8.4.1	Defining Individual Workout Steps	39
8.4.2	Defining Repeat Steps Example	40

8.4.3	Using Custom Target Values	42
9	Activity File	43
9.1	FIT Messages	44
9.1.1	Activity File Structure	45
9.1.2	Activity File Message Description.....	47
10	Activity Summary File	49
11	Course Files.....	50
11.1	FIT Messages	52
11.2	Course File Example.....	53
12	Goals File.....	56
12.1	FIT Messages	57
13	Totals File.....	58
13.1	FIT Messages	59
13.2	Totals File Example	59
14	Schedule File.....	61
14.1	FIT Messages	62
14.2	Schedule File Example	62
15	Monitoring File	64
15.1	FIT Messages	65
15.1.1	Monitoring File Definitions	66
15.1.2	Accumulated Values	66
15.2	Monitoring File Example	67
15.3	File Optimisation Options	69
15.3.1	Compressed Timestamp Headers	69
15.3.2	Data Record Compression.....	71
16	Daily Monitoring File.....	73

List of Figures

Figure 3-1. Device File.....	9
Figure 3-2. Device File Example	13
Figure 4-1. Settings File.....	14
Figure 5-1. Sport Settings File.....	16
Figure 5-2. Sport Settings File Example	19
Figure 6-1. Blood Pressure File	20
Figure 6-2. Multi-user BP File Example	23
Figure 6-3. Single User BP System	25
Figure 6-4. BP System without User Profile Support	26
Figure 7-1. Weight File	27
Figure 7-2. Multi-user Weight File Example.....	30
Figure 7-3. Single or Unidentified User Systems.....	32
Figure 8-1. Workout File	33
Figure 8-2. Defining Workout Steps.....	34
Figure 8-3. FIT workout and workout_step Message Structure	34
Figure 8-4. Example Workout_Steps	39
Figure 8-5. Workout_Steps for Repeating Steps.....	40
Figure 8-6. Repeat Steps Using "greater than" or "less than" Duration Types.....	41
Figure 8-7. Example Workout_Steps Using Custom Target Values	42
Figure 9-1. Activity File.....	43
Figure 9-2. Alternate Activity File Structure.....	46
Figure 10-1. Activity Summary File.....	49
Figure 11-1. Course File	50
Figure 11-2. Activity Record Messages Used to Create a "River Run" Course	51
Figure 11-3. "River Run" Course File with Laps and Course_points	51
Figure 11-4. Example record Data Messages of a Course File	53
Figure 11-5. Example lap and course_point Data Messages of a Course File.....	53
Figure 11-6. Example Course File.....	54
Figure 12-1. Goals File.....	56
Figure 13-1. Totals File.....	58
Figure 13-2. Totals File Example	60
Figure 14-1. Schedule File	61
Figure 14-2. Available Workout Files (file_id details)	62
Figure 14-3. Schedule File Example.....	63
Figure 15-1. Monitoring File.....	64
Figure 15-2. FIT Monitoring File Messages & Fields.....	67
Figure 15-3. Example FIT Monitoring File Data Records	68
Figure 15-4. Example FIT Monitoring File Data Records with Compressed Timestamp Headers	69

Figure 15-5. Example 1: Compressed Timestamp Headers & Data Record Compression	71
Figure 15-6. Example 2: Compressed Timestamp Headers & Further Data Compression	72
Figure 16-1. Daily Monitoring File.....	73

List of Tables

Table 1-1. Common FIT File Types.....	8
Table 3-1. FIT Messages Contained in Device File.....	10
Table 3-2. List of count_type and count Dynamic Field Values.....	11
Table 5-1. FIT Messages Contained in Sport Settings File.....	17
Table 6-1. FIT Messages Contained in BP File.....	21
Table 7-1. FIT Messages Contained in Weight File	28
Table 8-1. FIT Messages Contained in Workout File	35
Table 8-2. List of duration_types and Relevant Dynamic Field Values	37
Table 8-3. List of target_types and Relevant Dynamic Field Values	37
Table 8-4. Workout Intensity Values	38
Table 8-5. Expressing Heart Rate and Power in Specific and Relative Values	38
Table 9-1. FIT Messages Contained in an Activity File	44
Table 9-2. Activity File Message Descriptions.....	47
Table 11-1. FIT Messages Contained in Course File.....	52
Table 12-1. FIT Messages Contained in Goals File.....	57
Table 13-1. FIT Messages Contained in Totals File.....	59
Table 14-1. FIT Messages Contained in Schedule File	62
Table 15-1. Monitoring FIT File Messages and Fields.....	65
Table 15-2. FIT Monitoring File file_id.file_number Format.....	66
Table 16-1. FIT Daily Monitoring File file_id.file_number Format	74

1 Overview of the FIT File Protocol

Different applications of FIT files lead to a natural grouping of message based on purpose. This document describes FIT File Types, which consist of common message groupings and methods for best practice. Table 1-1 outlines the FIT file types covered in this document

Table 1-1. Common FIT File Types

FIT File Type	Purpose	File Type Number
Device	Describes a devices file structure and capabilities	1
Settings	Describes a user's parameters such as Age & Weight as well as device settings	2
Sport Settings	Describes a users desired sport/zone settings	3
Blood Pressure	Records blood pressure data	14
Weight	Records weight scale data	9
Workout	Describes a structured activity that can be designed on a computer and transferred to a display device to guide a user through the activity	5
Activity	Records data and events from active sessions	4
Activity Summary		20
Course	Uses data from an activity file to create a course	6
Goals	Describes a user's activity goals	11
Totals	Summarizes a user's total activity, characterized by sport	10
Schedule	Provides scheduling of workouts and courses	7
Monitoring	Records detailed monitoring data (i.e. logging interval < 24 Hr)	15
Daily Monitoring	Records daily summary monitoring data (i.e. logging interval = 24 hour)	28

2 Related Documents

The following supplementary documentation and files are provided in the SDK:

- Flexible & Interoperable Data Transfer (FIT) Protocol document
- FIT Global Messages and Fields (Profile.xls)
- FIT code generator
- FIT to CSV Conversion Tool
- Reference code examples
- Example FIT files

Many FIT applications will involve the ANT-FS protocol to facilitate the wireless transfer of FIT files. For further information regarding ANT-FS and related details for transferring FIT files specifically, refer to the following documents:

- ANT File Share (ANT-FS) Technology
- ANT-FS Reference Design and User Manual

3 Device File

The device file contains data records that provide information on a device's file structure/capabilities. The records provide details on the types of files a device supports, and restrictions/capabilities (if applicable) of the messages and fields contained within each file type (Figure 3-1).




Figure 3-1. Device File

3.1 FIT Messages

All FIT files must start with a file_id message. The FIT **file_id.type = 1** for a device file. The following FIT messages can also be included in a device file:

Table 3-1. FIT Messages Contained in Device File

FIT Message	FIT Fields	Required	Type	Value/Units
file_id (files from device)	type	Y	file (enum)	Device File (= 1)
	manufacturer	Y	Manufacturer (UINT16)	ANT+ managed. Please contact
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
file_id (files to device)	type	Y	file (enum)	Device File (= 1)
software	message_index	N	UINT16	Provides an index such that other FIT messages can be related to this message
	version	N	UINT16	
	part_number	N	String	
capabilities	languages	N	UINT8z	Array of languages supported (refer to language enum in profile.xls)
	workouts_supported	N	workout_capabilities (UINT32z)	Bit field describing the devices workout capabilities
file_capabilities	message_index	N	message_index (UINT16)	Provides an index such that other FIT messages can be related to this message
	type	N	file (enum)	Refer to profile.xls
	flags	N	file_flags (UINT8z)	Refer to profile.xls
	directory	N	string	String relating the directory name to which the associated file is stored
	max_count	N	UINT16	Maximum number of files that may be stored in the directory
	max_size	N	UINT32	Maximum size of the associated file type.
mesg_capabilities	message_index	N	message_index (UINT16)	Provides an index such that other FIT messages can be related to this message
	file	N	file (enum)	Refer to profile.xls
	mesg_num	N	mesg_num (UINT16)	Refer to profile.xls
	count_type	N	mesg_count (enum)	Refer to profile.xls
	count	N	UINT16	Dynamic field representing the message count. The value in this field depends on the count_type (refer to Table 3-2)
field_capabilities	message_index	N	message_index (UINT16)	Provides an index such that other FIT messages can be related to this message
	file	N	file (enum)	Refer to profile.xls

	mesg_num	N	mesg_num (UINT16)	Refer to profile.xls
	field_num	N	UINT8	Refer to profile.xls
	count	N	UINT16	Supported number of times the field may appear in the associated message

3.1.1 *software Message*

The software message describes the device's software version and part number.

3.1.2 *capabilities Message*

The capabilities message is used to communicate what languages a device supports and which workout functionalities are supported (if at all).

3.1.3 *file_capabilities Message*

The file_capabilities message can be used to indicate the device's directory structure (if applicable), the files stored within each directory, and may describe the content of the file. For example, this message may indicate a device has a "sports" directory that may contain up to 3 readable and writeable FIT sport files.

If a device does not have a directory structure, the device file shall be stored in the root directory.

3.1.4 *mesg_capabilities Message*

The mesg_capabilities message can be used to indicate the supported FIT messages within a specified FIT file. For example, this message may indicate a device has a settings file that may only contain a single user profile message.

If a specific FIT message is not described in the capabilities field for a supported file type, no assumptions can be made

3.1.4.1 *count Dynamic Field*

The count field is a dynamic field that is dependent on the value of the count_type field as described in Table 3-2.

Table 3-2. List of count_type and count Dynamic Field Values

count_type	Count value (dynamic field value)
num_per_file	num_per_file
max_per_file	max_per_file
max_per_file_type	max_per_file_type

3.1.5 *field_capabilities Message*

Most FIT fields appear once within a single FIT message; however, some FIT messages may support multiple appearances of the same field within a single message. If the latter is supported, the field capabilities message is used to indicate how many times the specified field may appear.

3.2 Device File Example

Figure 3-2 shows an example device file. The file begins with file_id definition and data messages, indicating the file is a device file (file_id.type = 1), the manufacturer is dynastream (file_id.manufacturer = 15), and the product is "1" with serial number "123456."

The device file then contains software definition and data messages indicating the device is operating software revision 1.01 (software.version = 101); and capabilities definition and data messages indicating interval workouts are supported provided a distance source exists (capabilities.workout_supported=0x00000201).

The file_capabilities message defines the device's file structure. In this case, the device has a /Settings directory that may contain a single, readable and writeable, settings file. An /Activities directory is also supported and may contain an unspecified number of readable activities files. Note that the activities directory is not writeable. Finally, the device has a /Weight directory that may contain a single, read only, weight file. There is no directory for the device file as it shall always be stored in the root directory.

In this example file, message capabilities are only defined for the settings file. The first mesg_capabilities message indicates a settings file shall only contain a single user_profile message per file. The following messages indicate a settings file may contain single hrm_profile and sdm_profile messages, and up to 2 bike_profile messages.

Finally, the field_capabilities messages indicates the settings file may not contain a user_profile.weight field (i.e. count = 0).

Note, all messages have been defined using a single local message type (i.e. local message type = 0), ensuring simple processors can handle all device file data.

file_id Definition Message (local message type=0, fields: type, mfg, product, serial_number)				
F	1	15	1	123456
software Definition Message (local message type=0, fields: version)				
S	101			
capabilities Definition Message (local message type=0, fields: workouts_supported)				
C	0x00000201			
file_capabilities Definition Message (local message type=0, fields: directory, type, max count, flags)				
FC	"Settings"	2	1	6
FC	"Activities"	4	0xFFFF	2
FC	"Weight"	9	1	2
mesg_capabilities Definition Message (local message type=0, fields: file, mesg_num, count_type, count)				
MC	2	3	0	1
MC	2	4	0	1
MC	2	5	0	1
MC	2	6	0	2
field_capabilities Definition Message (local message type=0, fields: file, mesg_num, field_num, count)				
DC	2	3	4	0

HEADER BYTE

(F: file_id, S: software C: capabilities FC: file_capabilities MC: mesg_capabilities DC: field_capabilities)

Figure 3-2. Device File Example

4 Settings File

The settings file contains data records that provide user and device information in the form of profiles. Each profile is grouped into either user, bike, or specific device profiles (such as HRMs, SDMs and activity monitors). The profiles provide information about the user, bicycle, sensors that a device may pair to, and user interface preferences (Figure 4-1).




Figure 4-1. Settings File

Currently settings files contain single user information. This file type may be extended in the future to allow for multi-user profiles.

4.1 FIT Messages

All FIT files must start with a file_id message. The FIT **file_id.type = 2** for a settings file. A FIT settings file also includes the following FIT messages:

device_settings

The device_settings message currently contains only the UTC offset, allowing for appropriate time coordination between devices.

user_profile

The user_profile message provides information about the user such that workout parameters can be properly set, and to allow for measurements dependent on user data (e.g. weight). Although most devices are single user, some devices such as weight scales and blood pressure monitors may support multiple users.

hrm_profile

The hrm_profile message is used in devices that interact with fitness equipment. It contains the device identification of the user's heart rate monitor that may already be paired with a device such as a watch. In this example, when the watch pairs with fitness equipment, a settings file containing the hrm_profile message is transferred to the fitness equipment allowing the fitness equipment to search for the user's specific heart rate monitor.

sdm_profile

Similar to the hrm_profile, the sdm_profile message contains the device identification of the user's stride based speed and distance monitor that may already be paired with a device such as a watch.

bike_profile

The bike_profile message provides information about the user's bicycle(s), and their associated devices such as speed, distance and power sensors. This allows related parameters to be properly set, and for measurements that dependent on bicycle information (e.g. wheel size). Multiple bike_profiles may be contained within a single settings file.

The file_id message, and at least one of the listed messages above, are the only required FIT messages in a settings file. Messages/fields are included on an "as needed" basis.

Note, all messages should be defined using a single local message type to ensure simple processors can handle all settings file data.

5 Sport Settings File

The sports settings file contains information about the user's desired target zones. The records provide details on the types of zones supported (such as heart rate or power), and the desired target levels. The sports settings file allows these values to be grouped by sport (Figure 5-1). There should only be one sport message per file.




Figure 5-1. Sport Settings File

5.1 FIT Messages

All FIT files must start with a file_id message. The FIT **file_id.type = 3** for a device file. Messages should be defined using a single local message type, ensuring simple processors can handle all sport file data. The following FIT messages can also be included in a sport file:

Table 5-1. FIT Messages Contained in Sport Settings File

FIT Message	FIT Fields	Required	Type	Value/Units
file_id (files from device)	type	Y	file (enum)	Sport File (= 3)
	manufacturer	Y	Manufacturer (UINT16)	ANT+ managed. Please contact
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
file_id (files to device)	type	Y	file (enum)	Sport File (= 3)
zones_target	max_heart_rate	N	UINT8	
	threshold_heart_rate	N	UINT8	
	functional_threshold_power	N	UINT16	
	hr_calc_type	N	hr_zone_calc	Refer to profile.xls
	pwr_calc_type	N	power_zone_calc	Refer to profile.xls
sport	sport	N	sport (enum)	Refer to profile.xls
	sub_sport	N	sub_sport (enum)	Refer to profile.xls
	name	N	String	
hr_zone	message_index	N	UINT16	Provides an index such that other FIT messages can be related to this message
	high_bpm	N	UINT8	
	name	N	String	
power_zone	message_index	N	message_index (UINT16)	Provides an index such that other FIT messages can be related to this message
	high_value	N	UINT16	
	name	N	String	
met_zone	message_index	N	message_index (UINT16)	Provides an index such that other FIT messages can be related to this message
	high_bpm	N	UINT8	
	calories	N	UINT16	Indicates the kcal/min to apply for metabolic calculation
	fat_calories	N	UINT8	Indicates the fat kcal/min to apply for metabolic calculation

5.1.1 zones_target Message

Some sport zone target values are calculated according to user parameters such as maximum or threshold heart rate or power values. The zones_target message is used to define these parameters, and shall only require one data message per file.

5.1.2 *sport Message*

The sport message indicates which sport, and/or sub sport, the zones are applicable for. There shall only be one sport data message per file. Refer to the FIT SDK for the list of available sports.

5.1.3 *hr_zone Message*

The hr_zone message is used to define the user's desired heart rate zones. Only the target maximum value is required to define a zone, and the minimum value will be set to the maximum of the previous zone. For example, if heart rate zone 1 high_bpm is set to 80 bpm, then zone 1 is defined as 0 to 80 bpm. Heart rate zone 2 may have high_bpm set to 110, resulting in a target zone 2 of 80 to 110 bpm.

The user may also define a name for each zone, such as "warm up" or "cool down."

5.1.4 *power_zone Message*

The power_zone message is used to define the user's desired power zones. Similar to heart rate, only the target maximum value is required to define a zone, and the minimum value will be set to the maximum of the previous zone; and the user may also define a name for each zone, such as "warm up" or "cool down."

5.1.5 *met_zone Message*

The met_zone message is used to define the user's desired metabolic zones. This allows the user to define targets based on heart rate, and the calories and/or fat calories per min calculation to apply when calculating metabolic burn.

5.2 Sport File Example

Figure 5-2 shows an example sport settings file. The file begins with file_id definition and data messages, indicating the file is a totals file (file_id.type = 10), the manufacturer is dynastream (file_id.manufacturer = 15), and the product is "1" with serial number "123456."

The sport file then contains the zones_target definition and data messages. In this case, the zones_target message specifies that the maximum heart rate for zone calculations is 180 bpm. The sport message then indicates the file is related to running activities.

Finally, the hr_zone message is used to define running heart rate based zones. The first zone is defined as heart rate below 89 bpm. The next zone is 90 to 106 bpm, followed by zones 107 to 124 bpm, 125 to 142 bpm, 143 to 159 bpm, 160 to 177 bpm and then anything above 178 bpm.

Note, all messages have been defined using a single local message type (i.e. local message type = 0), ensuring simple processors can handle all sport file data.

file_id Definition Message
(local message type=0, fields: type, mfg, product, serial number)

F	3	15	1	123456
---	---	----	---	--------

zones_target Definition Message
(local message type=0, fields: max_heart_rate)

Z	180
---	-----

sport Definition Message
(local message type=0, fields: sport)

S	1
---	---

hr_zone Definition Message
(local message type=0, fields: message_index, high_bpm)

HZ	0	89
HZ	1	106
HZ	2	124
HZ	3	142
HZ	4	159
HZ	5	177

HEADER BYTE

(F: file_id, Z: zones_target S: sport HZ: hr_zone)

Figure 5-2. Sport Settings File Example

6 Blood Pressure File

A blood pressure file contains time-stamped discrete measurement data. Data is reported after measurement, rather than a continuous real time format of data that is recorded in other file types such as activity files. The file is organized such that all definition messages are declared first, prior to recording any data messages. No definition messages should appear after data messages have been recorded. To link multiple data messages, they must have identical timestamps. Pairs of blood pressure and device information data messages are linked through common timestamps.

6.1 FIT Messages

All FIT files must start with a file_id message. The FIT **file_id.type = 14** for a blood pressure file. The BP file requires the file_id, and blood_pressure FIT messages (Figure 6-1). Other FIT messages, such as user_profile and device_info, may be included if desired.

The file_id definition and data messages should be recorded first, using the local message type 0. Local message type 0 should then be redefined for the FIT user_profile message (if used). The associated user_profile data messages should immediately follow the user_profile definition message. Once all relevant users have been recorded, local message type 0 should be redefined for blood_pressure messages. Using a single local message type to record the file_id, user_profile, and blood_pressure messages will ensure simple processors can handle all BP related data.

Once blood_pressure has been defined, any other desired FIT messages that will be recorded in the remainder of the file should also be defined in this section. The BP and other data messages shall fill the remainder of the file (Figure 6-1).




Figure 6-1. Blood Pressure File

The BP file must contain the FIT file_id, and blood_pressure messages as described in Table 6-1. It may also, optionally contain the user_profile and device_info message.

Table 6-1. FIT Messages Contained in BP File

FIT Message	FIT Fields	Required	Type	Value/Units
file_id (files from device)	type	Y	file (enum)	BP file (= 14)
	manufacturer	Y	Manufacturer (UINT16)	ANT+ managed. Please contact
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
file_id (files to device)	type	Y	file (enum)	BP file (= 14)
user_profile	message_index	N	UINT16	Provides an index such that other FIT messages can be related to this user
	local_id	N	UINT16	BP monitor's local user ID
	friendly_name	N	String	
	gender	N	Gender (enum)	Male/female
	age	N	UINT8	Years
	height	N	UINT8	1/100 m
	weight	N	UINT16	1/10 kg
	resting_heart_rate	N	UINT8	bpm
blood_pressure	timestamp	Y	Date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	user_profile_index	N	UINT16	Provides a link to the user_profile message. e.g. user_profile_index = 1 relates to the user_profile message with message_index = 1
	systolic_pressure	Y	mmHg (UINT16)	
	diastolic_pressure	Y	mmHg (UINT16)	
	mean_arterial_pressure	N	mmHg (UINT16)	
	heart_rate	Y	bpm (UINT8)	
	map_3_sample_mean	N	mmHg (UINT16)	
	map_morning_values	N	mmHg (UINT16)	
	map_evening_values	N	mmHg (UINT16)	
device_info	heart_rate_type	N	hr_type (enum)	normal, irregular
	timestamp	Y*	Date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	device_index	N	device_index (UINT8)	
	device_type	N	device_type (UINT8)	18 (0x12) for ANT+ BP monitor
	manufacturer	N	manufacturer (UINT16)	managed by ANT+ msb (i.e. bit 15) must be set to 1
device_info	serial_number	N	UINT32z	Managed by manufacturer

	product	N	UINT16	Managed by manufacturer
	software_version	N	UINT16	Managed by manufacturer
	hardware_version	N	UINT8	Managed by manufacturer
	cum_operating_time	N	UINT32	s
	battery_voltage	N	UINT16	1/256 V
	battery_status	N	battery_status (enum)	new/good/ok/low/critical

* Field is only required if the optional FIT message is recorded

As indicated in the "Required" column, not all of the listed fields shall be included in the BP file. At a minimum, the following is required:

- file_id message must be included to indicate the file type
- blood_pressure message containing systolic pressure, diastolic pressure and pulse (i.e. heart_rate)
- If the optional user_profile message is included, the file shall contain a user_profile message with a matching message_index defined for each user_profile_index used. If this message is not recorded, it is implied that user ID's are not supported on any level
- *If the optional device_info message is included, then it must contain the timestamp field in order to link each device_info message to its respective blood_pressure message

6.2 BP File Examples

Figure 6-2 shows an example FIT BP file. Note that the file contains the FIT 12 Byte header, definition and data messages for file_id, followed by the definition and data messages for user_profile, followed by the definition and data messages for blood_pressure and device_info. **Examples show a 12 Byte header, however, a 14 byte header is also applicable.**




Figure 6-2. Multi-user BP File Example

The `file_id`, `user_profile` and `blood_pressure` messages shall all use local message type 0 in order to minimize the RAM requirements for handling BP specific data on limited processors. Any other data messages, such as `device_info`, shall use a different local message type.

Note all user ID's must be defined prior to defining and recording measured data. The association of user information to `message_index` or `user_profile_index` may not change value within a file.

In this multi-user case, the file contains data from two users. One is a 47 year old male stored locally under user ID 4, and another is a 52 year old woman stored under local user ID 8. All of their data is recorded under their local user ID on the device, which is linked to their profile data. When the FIT file is written, the `user_profile` and `blood_pressure` data is linked through the `message_index` and `user_profile_index` fields respectively.

Note: `local_id` and `message_index` fields do not need to match; however, `message_index` and `user_profile_index` must match. The `message_index` field shall only be numbered sequentially from 0, in increments of 1. The number of local IDs a device has is dependent on the BP monitor's capabilities.

For a single user BP file, the `user_profile_index` does not need to be included in the `blood_pressure` message. Instead, the `local_id` can be defined once, using the `user_profile` message (with or without the `message_index` field), and all subsequent `blood_pressure` data records will be associated to that user. For example, in Figure 6-3, all data is associated to `local_id` "3". If the `blood_pressure` message is defined without the `user_profile_index` field, it is assumed that all data records that follow are associated to `user_profile_index` 0. Similarly, if the `message_index` field is not recorded and only one `user_profile` message exists, all `blood_pressure` data will be associated to that single user profile.

For simple BP monitors that do not support user ID's, the `user_profile` message is not required (Figure 6-4).




Figure 6-3. Single User BP System




Figure 6-4. BP System without User Profile Support

7 Weight File

A weight file is similar in structure to the BP File type. A weight file contains time-stamped discrete measurement data that is reported after measurement. The file is organized such that all definition messages are declared first, prior to recording any data messages. No definition messages should appear after weight data messages have been recorded. To link multiple data messages in a weight file, they must have identical timestamps (Figure 7-1).




Figure 7-1. Weight File

7.1 FIT Messages

All FIT files must start with a file_id message. The FIT **file_id.type = 9** for a weight file. A weight file must contain the FIT file_id, user_profile (if user profiles supported) and weight_scale messages as described in Table 7-1. It may also, optionally, contain the device_info message.

Table 7-1. FIT Messages Contained in Weight File

FIT Message	FIT Fields	Required	Type	Value/Units
file_id (files from device)	type	Y	file (enum)	Weight File (= 9)
	manufacturer	Y	manufacturer (UINT16)	ANT+ managed. Contact antalliance@thisisant.com for details
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
file_id (files to device)	type	Y	file (enum)	Weight File (= 9)
user_profile	message_index	N	UINT16	Provides an index such that other FIT messages in the file can be related to this user
	local_id	N	UINT16	Weight scale's local user ID
	friendly_name	N	string	
	gender	N	gender (enum)	Male/female
	age	N	UINT8	Years
	height	N	UINT8	1/100 m
	activity_class	N	activity_class(enum)	level/level_max/athlete
weight_scale	timestamp	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	user_profile_index	N	UINT16	Provides a link to the user_profile message. e.g. user_profile_index = 1 relates to the user_profile message with message_index = 1
	weight	Y	UINT16	1/100 kg
	percent_fat	N	UINT16	1/100 %
	percent_hydration	N	UINT16	1/100 %
	visceral_fat_mass	N	UINT16	1/100 kg
	bone_mass	N	UINT16	1/100 kg
	muscle_mass	N	UINT16	1/100 kg
	basal_met	N	UINT16	¼ kcal/day

	active_met	N	UINT16	¼ kcal/day
device_info	timestamp	Y*	Date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	device_index	N	device_index (UINT8)	
	device_type	N	device_type (UINT8)	18 (0x12) for ANT+ Weight scale
	manufacturer	N	manufacturer (UINT16)	managed by ANT+ msb (i.e. bit 15) must be set to 1
	serial_number	N	UINT32z	Managed by manufacturer
	product	N	UINT16	Managed by manufacturer
	software_version	N	UINT16	Managed by manufacturer
	hardware_version	N	UINT8	Managed by manufacturer
	cum_operating_time	N	UINT32	s
	battery_voltage	N	UINT16	1/256 V
	battery_status	N	battery_status (enum)	new/good/ok/low/critical

* Field is only required if the optional FIT message is recorded

As indicated in the “Required” column, not all of the listed fields shall be included in the weight file. At a minimum, the following is required:

- file_id message must be included to indicate the file type
- weight_scale message containing weight
- If the optional user_profile message is included, then the file shall contain a user_profile message with a matching message_index defined for each user_profile_index used. If this message is not recorded, it is implied that user ID’s are not supported on any level
- * If optional device_info message is included, then it must contain the timestamp field in order to link each device_info message to its respective blood_pressure message

7.2 Weight File Examples

Figure 7-2 shows an example FIT weight file. Note that the file contains the FIT 12 Byte header, definition and data messages for file_id, followed by the definition and data messages for user_profile, followed by the definition and data messages for weight_scale and device_info. **Examples show a 12 Byte header, however, a 14 byte header is also applicable.**




Figure 7-2. Multi-user Weight File Example

The file_id, user_profile and weight_scale messages shall all use local message type 0 in order to minimize the RAM requirements for handling weight scale data on limited processors. Any other data messages, such as device_info, shall use a different local message type as desired.

Note:

- **The association of user information to message_index or user_profile_index may not change value within a file.**
- **FIT files cannot be created/edited during a weight scale measurement**

In the example shown in Figure 7-2, the file contains data from two users. One is a 47 year old male stored locally under user ID 5, and another is a 52 year old woman stored under local user ID 6; which is indexed within the file to message_index 0 and 1 respectively. All of their data is recorded on the device under the local ID which is linked to their profile data. When the FIT file is written, the user_profile and weight_scale data is linked through the message_index and user_profile_index fields respectively

The number of local user ID's will be dependent on the weight scale devices capabilities (i.e. user profile ID). For simple weight scales that do not support user profiles, the user_profile message does not need to be included, indicating that the system that does not support user profiles.

For a single user weight file, the user_profile_index does not need to be included in the weight_scale message. Instead, the user information can be defined once, using the user_profile message (with or without the message_index and/or local_id fields), and all subsequent weight_scale data records will be associated to that user. For example, in Figure 7-3, all data is associated to the user information recorded in message_index "0". If the weight_scale message is defined without the user_profile_index field, it is assumed that all data records that follow are associated to user_profile_index 0. Similarly, if the message_index field is not recorded and only one user_profile message exists, all weight_scale data will be associated to that single user profile.

For simple weight scales that do not support user ID's, the user_profile message is not required




Figure 7-3. Single or Unidentified User Systems

8 Workout File

A workout file describes a structured activity that can be designed on a computer and transferred to a display device to guide a user through the activity. All FIT files must start with a file_id message. The FIT **file_id.type = 5** for a workout file.

The workout file should, at a minimum, contain the file_id, workout and at least one workout_step FIT messages (Figure 8-1). Messages should be defined and recorded sequentially, using only local message type 0. The file_id, and workout messages need only be recorded once, at the start of the workout file. The rest of the workout file will consist of multiple workout_step messages. Redefining local message type 0 for all messages will ensure simple processors can handle all workout data.




Figure 8-1. Workout File

Workouts are described as a series of steps. Each step is used to define a target effort for a set duration (Figure 8-2, step A and B), or to define a repetition pattern (Figure 8-2, step C).





Figure 8-2. Defining Workout Steps

The following sections will describe the FIT messages of a workout file.

8.1 FIT Messages

The general message structure for both the workout and workout_step messages are show below in Figure 8-3.

FIT workout message:



FIT workout_step message:




Figure 8-3. FIT workout and workout_step Message Structure

The full list of FIT messages and fields contained in a workout file are outlined in Table 8-1. Note that not all fields are required.

Table 8-1. FIT Messages Contained in Workout File

FIT Message	FIT Fields	Required	Type	Value/Units
file_id (files from device)	type	Y	file (enum)	Workout file (= 5)
	manufacturer	Y	manufacturer (UINT16)	ANT+ managed. Contact antalliance@thisisant.com for details
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
	time_created	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
file_id (files to device)	type	Y	file (enum)	Workout file (= 5)
	manufacturer	Y	manufacturer (UINT16)	ANT+ managed. Contact antalliance@thisisant.com for details
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
	time_created	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
workout	sport	N	sport (enum)	Indicates type of sport workout
	capabilities	N	UINT32z	Bitfield describing workout capabilities. Refer to SDK
	num_valid_steps	Y	UINT16	Indicates the number of valid steps contained in the file
	wkt_name	N	String	User friendly string identifying name of workout
workout_step	message_index	Y	UINT16	Provides an index for each step such that a repeat step can refer back to a specific workout step
	wkt_step_name	N	String	User friendly string identifying name of the workout step
	duration_type	Y	wkt_step_duration (enum)	Indicates the type of parameter that will define the workout steps' duration.
	duration_value	N	UINT32, workout_hr, or workout_power	Dynamic field representing the value of the duration. The value in this field depends on the duration_type (Table 8-2)
	target_type	Y	wkt_step_target (enum)	Indicates the type of parameter that will define the workout steps' target range/zone.
	target_value	N	UINT32, workout_hr, or workout_power	Dynamic field representing the value of the target. The value in this field depends on either duration_type or target type as outline in Table 8-3.

	custom_target_value_low	N	UINT32, workout_hr, or workout_power	If the workout target uses a custom range, rather than a defined zone, this field is used to specify the lower boundary. Dynamic field dependent on target_type (Table 8-3)
	custom_target_value_high	N	UINT32, workout_hr, or workout_power	If the workout target uses a custom range, rather than a defined zone, this field is used to specify the upper boundary. Dynamic field dependent on target_type (Table 8-3)
	intensity	N	intensity (enum)	Represents the workout steps intensity level (Table 8-4)

8.2 Workout Message

The workout message is recorded once, at the start of the file and provides a summary of the workout information contained in the file. It describes the sport the workout is related too, workout capabilities, and the number of defined workout steps contained in the file. Using the Figure 8-2 example, the number of defined steps is 3 (i.e. steps A, B and C).

8.3 Workout_steps Message

The workout_steps message is used to define each workout step. For defining a single step, this message describes:

- Duration type: e.g. time, distance, etc
- Duration value: e.g. 1min, 100m, etc
- target type: e.g. heart rate, speed, etc
- target value: this may be a preconfigured zone (e.g. heart rate zone '1' or '2') or a custom value (e.g. 65% to 75% max heart rate)

For defining a repetition step, this message describes:

- Duration type: repeat a sequence of workout_steps
- Duration value: the step to start repetitions from (i.e. step A in Figure 8-2)
- target value: number of repeats, time limit of repeats, etc

The workout_steps message contains dynamic fields which are described in sections 8.3.1 and 8.3.2.

8.3.1 *Duration_type Dynamic Fields*

The duration_value and target_value fields are dynamic fields that are dependent on the value of the duration_type field as described in Table 8-2.

Table 8-2. List of duration_types and Relevant Dynamic Field Values

duration_type	duration_value (dynamic field value)	target_value (dynamic field value)
Time	duration_time	
Distance	duration_distance	
hr_less_than	duration_hr	
hr_greater_than	duration_hr	
Calories	duration_calories	
Open	duration_value	
repeat_until_steps_cmplt	duration_step	repeat_steps
repeat_until_time	duration_step	repeat_time
repeat_until_distance	duration_step	repeat_distance
repeat_until_calories	duration_step	repeat_calories
repeat_until_hr_less_than	duration_step	repeat_hr
repeat_until_hr_greater_than	duration_step	repeat_hr
repeat_until_power_less_than	duration_step	repeat_power
repeat_until_power_greater_than	duration_step	repeat_power
power_less_than	duration_power	
power_greater_than	duration_power	

8.3.2 *Target_type Dynamic Fields*

The target_value, and custom_target_low/high fields are dynamic fields that are dependent on the value of the target_type field as described below in Table 8-3.

Table 8-3. List of target_types and Relevant Dynamic Field Values

target_type	target_value (dynamic field value)	custom_target_low (dynamic field value)	custom_target_high (dynamic field value)
speed		custom_target_speed_low	custom_target_speed_high
heart_rate	target_hr_zone	custom_target_heart_rate_low	custom_target_heart_rate_high
open	target_value	custom_target_value_low	custom_target_value_high
cadence	target_cadence_zone	custom_target_cadence_low	custom_target_cadence_high
power	target_power_zone	custom_target_power_low	custom_target_power_high
grade			
resistance			

8.3.3 *Target values vs Custom target values*

Unless defining repeat steps, the target_value dynamic field typically refers to setting a target zone. These target zones represent target limits that have already been established through other means; such as: predefined on fitness equipment, in a settings file, or through a user interface. The workout_step can then be used to set a target heart rate, power or other

zone value. If a specific target range is desired, the custom_target_low and custom_target_high fields may be used to set the upper and lower boundaries of the desired target range. Refer to the FIT SDK for specific field/zone values.

8.3.4 Workout Intensity

The workout_steps intensity field differentiates between sets that are designated for warm up, recovery, active and cool down. The intensity field does not affect target or duration values, but tracking the intensity field allows the program designer to calculate the total amount of active time within a workout.

Table 8-4. Workout Intensity Values

Intensity Value	Intensity Description
0	Active
1	Rest
2	Warmup
3	Cooldown

8.3.5 Setting Power and Heart Rate Values

Power and heart rate values can be set as specific or relative values. Specific values are set in integer values representing beats per minute (bpm) for heart rate, or watts for power. Relative values are set as an integer value ranging from 0 to 100% of the user's maximum heart rate or 0 – 1000% functional threshold power (ftp).

As the integers 0 to 100 (heart rate) and 0 to 1000 (power) range are reserved for relative values, specific heart rate and power values must be incremented by 100 bpm or 1000 watts respectively. Examples are provided below.

Table 8-5. Expressing Heart Rate and Power in Specific and Relative Values

Desired Heart Rate	Value in HR Field	Desired Power	Value in Power Field
125 bpm	225	325 Watts	1325
85% user's max HR	85	275%	275

8.4 Workout File Examples

The following examples illustrate how to correctly define workout steps, from setting individual steps to repeating steps, and setting custom target values.

8.4.1 Defining Individual Workout Steps

Figure 8-4 shows an example of four workout_steps records used to define a workout that has a warmup step ("A"), two active steps ("B1" and "B2"), and a cooldown step ("C").




Figure 8-4. Example Workout_Steps

Message_index values always start at 0, and increment with each workout_step message. As such, the first workout_step message uses message_index 0. The duration_type is set to 0 (i.e. time), which means the duration_value dynamic field will contain duration_time data, which is a time value in units of milliseconds. Similarly, the target_type is set to 1 (i.e. heart rate) and the target_value field will refer to target_hr_zone data, which is an integer value representing the pre-defined zone. As the target zone is defined, no custom values are required and shall be set to 0. The intensity field is set to 2, indicating the step is a warmup step. In this case, the duration is set to 60 seconds of activity to be performed in heart rate zone 2.

Workout_steps "B1" and "B2" are indexed at message_index 1 and 2 respectively. For both steps, the duration_type is set to 1 (i.e. distance), which means the duration_value dynamic field will contain duration_distance data, which is a distance value in units of centimeters. Similarly, the target_type is set to 4 (i.e. power) and the target_value field will refer to

target_power_zone data, which is an integer value representing the pre-defined zone. As the target zones are defined, no custom values are required and shall be set to 0. The intensity field is set to 0, indicating these are active steps. In this case, the duration is set to 500 meters seconds of activity each to be performed in power zone 5, and then 3.

The final workout_step "C" is at message_index 3, the duration_type is set to 3, indicating the duration_type is "hr_less_than" and the duration_value will refer to duration_hr data. This means that the step will be performed for as long as it takes the user's heart rate to drop below that of the specified hr value (in duration_hr). The target_type is set to 4 (i.e. power) and the target_value field will refer to target_power_zone data, which is an integer value representing the pre-defined zone. As the target zones are defined, no custom values are required and shall be set to 0. The intensity field is set to 3, indicating this is a cooldown step. In this case, the user will perform the activity in power zone 1, until the user's heart rate is below 125 bpm. NB that the duration_hr value is the target value + 100 (i.e. 125 + 100 bpm), refer to section 8.3.5 for details on setting heart rate or power values.

8.4.2 Defining Repeat Steps Example

Figure 8-5 uses the same steps from the example in Figure 8-4, however another step ("Rep") is added to repeat the active steps ("B1" and "B2"). Note that the added step has changed the message_index value for step "C" from 3 to 4. This is because **the message_index field must be sequential**.

0	"A"	0	60,000	1	2	0	0	2
1	"B1"	1	50,000	4	5	0	0	0
2	"B2"	1	50,000	4	3	0	0	0
3	"Rep"	6	1	2	3	0	0	0
		(rep' until steps cmplt)	(duration_step) Repeat from msg_index 1	(open)	(repeat_steps) 3 times	(custom_target_low)	(custom_target_high)	(active)
4	"C"	2	225	4	1	0	0	3




Figure 8-5. Workout Steps for Repeating Steps

The repeat workout step ("Rep") has a duration_type value of 6, meaning "repeat_until_steps_completed", and the duration_value will be of type duration_step, and will contain the message_index of the step to start the repetitions from. In

other words, setting the duration_step field to a value of 1, will indicate that the repetition will start from the workout_step with a message_index = 1 (i.e. step "B1"), and follow through all subsequent steps up until the repeat step. In this case, this means steps "B1" and "B2" will be repeated. For repeat steps, the duration_type also determines the value in the target_value dynamic field, and indicates this field will contain repeat_steps data, which is an integer value representing the number of times the sequence shall be repeated before progressing onto the next step (i.e. "C").

For repeat steps that use duration_types containing "repeat_until_[type]_greater than" or "repeat_until_[type]_less than", the sequence will repeat until the specified value met, drop out of the current step and immediately drop into the next step. This scenario is illustrated in Figure 8-6.

0	"A"	0	60,000	1	2	0	0	2
1	"B1"	1	50,000	4	5	0	0	0
2	"B2"	1	50,000	4	3	0	0	0
3	"Rep"	11	1	1	80	0	0	0
		(rep' until hr >)	(duration_step) Repeat from msg_index 1	(hr)	(repeat_hr) Hr > 80% max hr	(custom_target_low)	(custom_target_high)	(active)
4	"C"	2	225	4	1	0	0	3




Figure 8-6. Repeat Steps Using "greater than" or "less than" Duration Types.

Step "Rep" has now been defined using duration_type value of 11, meaning "repeat_until_hr_greater_than", and the duration_value will be of type duration_step, and will again contain the message_index of the step to start the repetitions from. The duration_step field is again set to a value of 1, indicating the repetition will include steps "B1" and "B2". For repeat steps, the duration_type also determines the value in the target_value dynamic field, and indicates this field will contain repeat_hr data, refer to section 8.3.5 for details on setting heart rate or power values. In this case, repeat_hr is set to 80, indicating that the steps will be repeated until the user's heart rate is greater than 80% of their maximum heart capacity. Once this heart rate has been exceeded, the workout jumps out of the current step (i.e. "B2") and commences the next step (i.e. "C").

8.4.3 Using Custom Target Values

If predefined target zones are unavailable or undesired, custom target values may be used instead. Figure 8-7 below uses the same workout steps from the example in Figure 8-4, however custom target values are used instead of target zones.

If custom targets are used, the relevant `target_value` field (i.e. `target_hr` zone and `target_power` zone in the example below) shall be set to 0, indicating that custom values will be used. The data type of the custom values is dependent on the `target_type` as described in Table 8-3.




Figure 8-7. Example Workout Steps Using Custom Target Values

In this example, step "A" `target_type` is set to 1 (i.e. heart rate) and the `target_value` field is set to zero indicating custom values will be used. The `custom_value_low` and `custom_value_high` fields will be of `custom_heart_rate_low` and `custom_heart_rate_high` data types respectfully, setting a target heart rate range of 50-60% of the user's maximum heart rate.). Refer to section 8.3.5 for details on setting heart rate or power values.

Similarly, workout_steps "B1", "B2" and "C" the `target_type` is set to 4 (i.e. power) and the `target_value` field set to 0 for custom target values. The `custom_value_low` and `custom_value_high` fields will be of `custom_power_low` and `custom_power_high` data types respectfully, setting a target speed range of 300 to 310 Watts for "B1", 260 to 270 Watts for "B2" and 220 to 230 Watts for step "C".

9 Activity File

Activity files are used to record sensor data and events from an active session. The basic structure of an activity file is shown in (Figure 9-1).




Figure 9-1. Activity File

An activity file shall contain file_id, activity, session, and lap messages. The file may also contain record, event, length and/or hrv messages.

All data messages in an activity file (other than hrv) are related by a timestamp.

9.1 FIT Messages

All FIT files must start with a file_id message. The FIT **file_id.type = 4** for an activity file. A partial list of FIT messages and fields contained in an activity file are outlined in Table 9-1. For a full list of activity file messages and fields refer to the FIT SDK. Note, only data message requirements of the activity file are included in Table 9-1.

Table 9-1. FIT Messages Contained in an Activity File

FIT Message	FIT Fields	Required	Type	Value/Units
file_id	type	Y	file (enum)	Activity file (= 4)
	manufacturer	Y	manufacturer (UINT16)	ANT+ managed. Contact antalliance@thisisant.com for details
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
	time_created	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
activity	timestamp	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	num_sessions	Y	uint16	Indicates total number of sessions included in the activity file
	type	Y	activity (enum)	refer to SDK
	event	Y	event (enum)	refer to SDK
	event_type	Y	event_type (enum)	refer to SDK

session	timestamp	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	start_time	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	total_elapsed_time	Y	UINT32	Total number of msec since timer started (includes pauses)
	sport	Y	sport (enum)	refer to SDK
	event	Y	event (enum)	refer to SDK
	event_type	Y	event_type (enum)	refer to SDK

lap	timestamp	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	event	Y	event (enum)	refer to SDK
	event_type	Y	event_type (enum)	refer to SDK

length	timestamp	Y*	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time

	event	Y*	event (enum)	refer to SDK
	event_type	Y*	event_type (enum)	refer to SDK

record	timestamp	Y*	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time

event	timestamp	Y*	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	event	Y*	event (enum)	refer to SDK
	event_type	Y*	event_type (enum)	refer to SDK

device_info	timestamp	Y*	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time

hrv	time	Y*	UINT16	Refer to section Error! Reference source not found.


* Only required if optional message included

Note that the activity file makes use of dynamic fields, meaning the interpretation of some message fields will depend on the value of another field. For example, Field Definition #10 of the Session message is Total_Cycles. However, if the sport is Running, Total_Cycles should be interpreted at Total_Strides where it would be interpreted as Total_Strokes if the sport is rowing.

9.1.1 Activity File Structure

The activity file shall adhere to the following rules:

- An activity file contains one activity message.
- Multiple Session messages may be recorded for a single activity.
- Multiple Laps may be recorded for a single session.
- Multiple Lengths may be recorded for a single lap.
- The activity, session, lap, lengths summary messages may be grouped together at the start of the file (Figure 9-2) or interleaved with record, event, hrv messages (Figure 9-1). In either case these summary messages must be in chronological order.
- Record, event and hrv messages must be in chronological order.

**Figure 9-2. Alternate Activity File Structure**

9.1.2 Activity File Message Description

An overview of the FIT activity file messages and fields is provided in Table 9-2.

Table 9-2. Activity File Message Descriptions

FIT Message	Description
activity	Provides a high level description of the overall activity file. This includes overall time, number of sessions and the type of each session
session	Provides more summary detail including totals and averages over the entire session.
lap	Provide summary detail over the duration of a single lap. A lap breaks a session into segments of interest and could be based on distance, time, user action (i.e. button press), even landmarks or waypoints.
length	Provide summary detail over the duration of a single length. A length is a set distance such as the length of a pool, the length of a track/circuit.
record	Provide relatively high resolution, time-stamped data about the activity. This message carries instantaneous data such as speed, position, heart rate and bicycle power. Record messages must be in chronological order
event	Used to record events within an activity including starting and stopping the timer. The event message can also record alerts. Event messages must be in chronological order
hrv	Used to record heart rate variability data. hrv data messages contain an array of RR intervals and are interleaved with record and event messages in chronological order
device_info	Used to record information about the device such as battery live and operating time

9.1.2.1 Record Messages

The majority of activity data is stored using the record message. The record message allows information such as position (latitude, longitude), speed, heart rate, etc to be stored.

Accumulating fields shall NOT be reset to zero at any point within an activity file. These are fields such as distance, compressed_speed_distance, accumulating_power and compressed_accumulating_power. Some legacy devices have implemented a reset to zero in the record.distance field at the end of an individual session. In order to maintain reverse compatibility, when decoding the record.distance field, session boundaries shall be checked. If the record.distance field is set to zero at a session boundary, the decoder shall interpret this as a reset to 0 event and NOT a rollover event.

All records shall be timestamped (using either the timestamp field, or compressed timestamp headers).

9.1.2.2 Event Messages

Event messages may be present throughout an activity file to indicate the presence of events such as timer start/stop, battery status, course points, alerts, etc. Most events are recorded using the FIT event message; however, Session, lap, and length messages are a special type of event message as described in the next sub section.

All events shall be timestamped and include both the event and event_type fields. Certain events shall have additional data options or requirements. For example, the recovery_hr event shall only occur after a session stop. The duration of the recovery is determined by the manufacturer.

9.1.2.3 Summary Messages

The session, lap, and length messages provide summaries of specific sections of an activity as described in Table 9-2. These summary messages also serve as session, lap and length event messages.

9.1.2.4 HRV Data

Heart Rate Variability (HRV) data may be recorded in an activity file. The hrv data message is an array of RR interval values. All hrv messages contained within the activity file shall be concatenated together into a single, large array of data. Note that

hrv data is not timestamped, and shall be synchronized by checking successive RR intervals as they occur between timestamp activity “record” data.

Some devices require the HRV functionality to be enabled by the user. This can be achieved using a settings file, by including the hrm_profile message and setting the log_hrv field to true.

10 Activity Summary File

Activity summary files are a compact version of activity file and contain only activity, session and lap messages (Figure 9-1). The FIT **file_id.type = 20 (0x14)** for an activity summary file.




Figure 10-1. Activity Summary File

Activity summary file follows the same requirements as for an activity file:

- Only a single activity message shall be recorded.
- Multiple session messages may be recorded for a single activity message.
- Multiple lap messages may be recorded for each session message.
- The required fields for activity, session and lap messages are the same as in Table 9-1.

11 Course Files

A course file contains data from a recorded activity that can be transferred to a display device to guide a user through the same activity. All FIT files must start with a file_id message. The FIT **file_id.type = 6** for a course file.

The course file should, at a minimum, contain the file_id, lap, record, and course FIT messages; and may optionally contain the course_point message (Figure 11-1).

The file_id, course, lap, and optional course_point messages shall be defined and recorded sequentially, using only local message type (i.e. 0). The file_id, and course messages need only be recorded once, at the start of the course file. At least one lap message will be recorded in each course file; however multiple lap messages may be recorded if desired. Redefining local message type 0 for all of these messages will ensure simple processors can handle all course data. The rest of the course file will consist of multiple record messages detailing the course (Figure 11-1).




Figure 11-1. Course File

Course files contain a series of activity record data messages which can be used by a display, or fitness console, to recreate the activity for the same, or different, users to repeat (Figure 11-2). Record messages may contain positional information such as latitude, longitude and altitude; user information such as speed, heart rate and power; as well as information such as current distance and temperature. Each record is used to create a point along the course.




Figure 11-2. Activity Record Messages Used to Create a "River Run" Course

Course files also contain lap and course_point messages to provide summary activity data, and key course milestones and/or landmarks. Figure 11-3 shows the example "River Run" course file with lap and course_point messages.




Figure 11-3. "River Run" Course File with Laps and Course_points

11.1 FIT Messages

The list of FIT messages and fields contained in a course file are outlined in Table 11-1. Note that not all fields are required.

Table 11-1. FIT Messages Contained in Course File

FIT Message	FIT Fields	Required	Type	Value/Units
file_id (files from device)	type	Y	file (enum)	Course File (=6)
	manufacturer	Y	manufacturer (UINT16)	ANT+ managed. Contact antalliance@thisisant.com for details
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
	time_created	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
file_id (files to device)	type	Y	file (enum)	Course File (=6)
	manufacturer	Y	manufacturer (UINT16)	ANT+ managed. Contact antalliance@thisisant.com for details
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
	time_created	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
course	sport	N	sport (enum)	Type of sport course relates to
	name	Y	string	Name of course
	capabilities	N	course_capabilities (enum)	Indicates content of course file
course_point	message_index	N	message_index (UINT16)	Provides an index for each course point
	timestamp	Y*	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	position_lat	N	SINT32	Semicircles
	position_long	N	SINT32	Semicircles
	distance	N	UINT32	1/100 m
	type	N	course_point (enum)	Refer to FIT SDK for course types
	name	N	string	
lap**	timestamp	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	start_time	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	total_distance	N		
	...			
record**	timestamp	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	distance	Y		
	position_lat	N		
	position_long	N		
	...			

* Only required if optional message included

** Fields for FIT message only partially listed. Refer to FIT SDK for full listing.

11.2 Course File Example

Figure 11-4 shows a 9.5 km running activity that shall be used to create the example course file. Each point along the course is represented by one of the activity file's "record" messages, which consists of positional, distance and user information.




Figure 11-4. Example record Data Messages of a Course File

Each record has an associated timestamp, latitude and longitude position, distance run, and the user's heart rate. For simplicity the actual lat/long coordinates are represented by "XXX".

In this case, four laps events were also recorded, each representing a 2km distance completed (Figure 11-5). Each lap message contains the lap start/end times, and the user's maximum and average heart rate. This example also utilises the FIT course_point message to represent the start, halfway and end points of the course.



Figure 11-5. Example lap and course_point Data Messages of a Course File

file_id Definition Message (local message type=0)					
F	6	X	1234	timestamp_created	
course Definition Message (local message type=0)					
C	"River Run"				
lap Definition Message (local message type=0)					
L	timestamp_L1	timestamp_0	121	138	
L	timestamp_L2	timestamp_L1	134	143	
L	timestamp_L3	timestamp_L2	145	151	
L	timestamp_L4	timestamp_L3	146	153	
L	timestamp_end	timestamp_L4	133	147	
course_point Definition Message (local message type=0)					
CP	timestamp_0	"start"			
CP	timestamp_X	"halfway"			
CP	timestamp_end	"end"			
record Definition Message (local message type=0)					
R	timestamp_0	XXX	XXX	0	72
⋮					
R	timestamp_L1	XXX	XXX	200000	128
⋮					
R	timestamp_l	XXX	XXX	284502	128
R	timestamp_m	XXX	XXX	284558	124
R	timestamp_n	XXX	XXX	284615	121
R	timestamp_o	XXX	XXX	284659	125
⋮					
R	timestamp_L2	XXX	XXX	400000	128
⋮					
R	timestamp_X	XXX	XXX	450000	128
⋮					
R	timestamp_L3	XXX	XXX	600000	128
⋮					
R	timestamp_L4	XXX	XXX	800000	128
⋮					
R	timestamp_end	XXX	XXX	950000	125

HEADER BYTE (F: file_id, C: course, L: lap, CP: course_point, R: record)

Figure 11-6. Example Course File

The resultant course file is formatted as shown in Figure 11-6.

- In this example, each lap and course_point message can be associated to a record message through a matching timestamp. As such, each lap or course_point message does not need to contain any positional, distance, or heart rate data as this can be obtained from the matching record.
- Every definition and data message in this example uses local message type 0, ensuring simple processes can handle all course data
- Record messages are stored in chronological order

12 Goals File

Goals files allow a user to communicate their exercise/health goals. Goals may be set for a variety of activities, over specific period of time, and with desired targets set according to total duration, calories consumed, distance travelled, number of steps taken and/or frequency of activity (Figure 12-1). Multiple goals may be set, and grouped according to sport.




Figure 12-1. Goals File

12.1 FIT Messages

All FIT files must start with a file_id message. The FIT **file_id.type = 11** for a goals file. The following FIT messages can also be included in a goals file.

Table 12-1. FIT Messages Contained in Goals File

FIT Message	FIT Fields	Required	Type	Value/Units
file_id (files from device)	type	Y	file (enum)	Goals File (= 11)
	manufacturer	Y	Manufacturer (UINT16)	ANT+ managed. Please contact
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
file_id (files to device)	type	Y	file (enum)	Goals File (= 11)
goal	message_index	N	UINT16	Provides an index such that other FIT messages can be related to this message
	sport	N	sport (enum)	Type of sport relating to reported goals
	sub_sport	N	sub_sport (enum)	Type of sub sport relating to reported goals
	start_date	N	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	end_date	N	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	type	N	goal (enum)	Refer to profile.xls
	value	N	UINT32	
	repeat	N	BOOL	
	target_value	N	UINT32	
	recurrence	N	goal_recurrence (enum)	Refer to profile.xls
	recurrence_value	N	UINT16	Total calories consumed during recorded activity
	enabled	N	BOOL	

Goal messages indicate the user's goal for a specific sport (if applicable) and subsport (if applicable)

13 Totals File

Totals files are used to summarize a user's activities and may contain multiple totals messages each representing summaries of a different activity type/sport (Figure 13-1).




Figure 13-1. Totals File

13.1 FIT Messages

All FIT files must start with a file_id message. The FIT **file_id.type = 10** for a totals file. The following FIT messages can also be included in a totals file.

Table 13-1. FIT Messages Contained in Totals File

FIT Message	FIT Fields	Required	Type	Value/Units
file_id (files from device)	type	Y	file (enum)	Totals File (= 10)
	manufacturer	Y	Manufacturer (UINT16)	ANT+ managed. Please contact
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
file_id (files to device)	type	Y	file (enum)	Totals File (= 10)
totals	message_index	N	UINT16	Provides an index such that other FIT messages can be related to this message
	timestamp	Y	date_time (UINT32)	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	timer_time	N	UINT32	Total time of activities, excluding pauses/rests
	distance	N	UINT32	Total distance covered during recorded activities
	calories	N	UINT32	Total calories consumed during recorded activities
	sport	Y	sport (enum)	

Totals messages indicate the user's total amount of recorded distance, calories, and/or active time and may be grouped by sport type, such as running, cycling fitness equipment, etc.

13.2 Totals File Example

Figure 13-2 shows an example totals file. The file begins with file_id definition and data messages, indicating the file is a totals file (file_id.type = 10), the manufacturer is dynastream (file_id.manufacturer = 15), and the product is "1" with serial number "123456."

The totals file then contains the totals definition and data messages. In this case, the totals message includes message_index, timestamp, timer time, distance and sport. The file indicates totals data is available for three sports: generic (sport=0), running (sport=1) and cycling (sport=2).

The user has not performed any generic or cycling activity with the totals fields indicating 0 total timer time and distance. However, the data shows the user has performed 1167 seconds worth of running, covering 4669m.

file_id Definition Message

(local message type=0, fields: type, mfg, product, serial_number)

F	10	15	1	123456
---	----	----	---	--------

totals Definition Message

(local message type=0, fields: msg_index, timestamp, timer time, distance, sport)

T	0	timestamp_X	0	0	0
---	---	-------------	---	---	---

T	1	timestamp_X	1167	4669	1
---	---	-------------	------	------	---

T	2	Timestamp_X	0	0	2
---	---	-------------	---	---	---

HEADER BYTE

(F: file_id, T: totals)

Figure 13-2. Totals File Example

14 Schedule File

Schedule files are used to schedule a user's workouts and may contain multiple schedule messages each representing the start time completion of a workout (Figure 14-1). A single workout, or multiple workouts, may be scheduled multiple times within a schedule file. Multiple courses or workouts may also be scheduled at the same time.




Figure 14-1. Schedule File

Schedule messages do not have to be recorded chronologically; however, this is a recommended best practice.

14.1 FIT Messages

All FIT files must start with a file_id message. The FIT **file_id.type = 7** for a schedule file. The following FIT messages can also be included in a schedule file.

Table 14-1. FIT Messages Contained in Schedule File

FIT Message	FIT Fields	Required	Type	Value/Units
file_id (files from device)	type	Y	file (enum)	Schedule File (= 7)
	manufacturer	Y	manufacturer (UINT16)	ANT+ managed. Please contact
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
file_id (files to device)	type	Y	file (enum)	Schedule File (= 7)
schedule	manufacturer	Y	manufacturer (UINT16)	Corresponds to file_id.manufacturer of scheduled workout/course
	product	Y	UINT16	Corresponds to file_id.product of scheduled workout/course
	serial_number	Y	UINT32z	Corresponds to file_id.serial_number of scheduled workout/course
	time_created	Y	date_time	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	completed	N	BOOL	Indicates if the scheduled item has been completed
	type	Y	schedule (enum)	Indicates if schedule is for a workout or course file
	scheduled_time	Y	local_date_time	Seconds since 00:00 Dec 31 1989 local time

Schedule messages indicate the time at which a specific workout or course should commence. The schedule message references the file_id of the course/workout that is to be performed.

14.2 Schedule File Example

For this example, assume the device has three FIT workout files, with file_id messages as shown in Figure 14-2.

Workout File A		Workout File B	
file_id.manufacturer	= 15	file_id.manufacturer	= 15
file_id.product	= 1	file_id.product	= 1
file_id.serial_number	= 12345	file_id.serial_number	= 12345
File_id.time_created	= Timestamp_X1	File_id.time_created	= Timestamp_X2
Workout File C			
file_id.manufacturer	= 15		
file_id.product	= 1		
file_id.serial_number	= 12345		
File_id.time_created	= Timestamp_X3		

Figure 14-2. Available Workout Files (file_id details)

15 Monitoring File

Monitoring files are used to store data that is logged over varying time intervals. The actual data that is stored may vary depending on use case (Figure 15-1). Additional device_information (such as battery_status) may also be stored.




Figure 15-1. Monitoring File

15.1 FIT Messages

Activity monitoring data is stored in a FIT monitoring file. The FIT **file_id.type = 15** for a monitoring file. The monitoring file must contain the FIT file_id and monitoring messages as described in the FIT File Types document.

Table 15-1. Monitoring FIT File Messages and Fields

FIT Message	FIT Fields	Required	Type	Value/Units
file_id	type	Y	file (enum)	Monitoring File = 15
	manufacturer	Y	manufacturer (UINT16)	ANT+ managed. Contact antalliance@thisisant.com for details
	product	Y	UINT16	Managed by manufacturer
	serial_number	Y	UINT32z	Managed by manufacturer
	time_created	Y	date_time	Time file was created. Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	file_number	Y	UINT16	Indicates the type of monitoring file. Refer to section 15.1.1.
monitoring_info	timestamp	N	date_time	Seconds since UTC 00:00 Dec 31 1989 If <0x10000000 = system time
	local_timestamp	N	local_date_time	Seconds since 00:00 Dec 31 1989 Local Time
monitoring	timestamp	Y	date_time	Time of measurement recording
	device_index	N	device_index (UINT8)	Associates data to a specific device, not required for a file associated with a single device.
	calories	N	UINT16	Accumulated calories (cals)
	distance	N	UINT 32	Accumulated distance
	cycles	N	UINT 32	Accumulated cycles
	active_time	N	UINT 32	Accumulated active time
	activity_type	N	activity_type	Refer to profile.xls
	activity_subtype	N	activity_subtype	Refer to profile.xls
	activity_level	N	activity_level (enum)	Measure of activity. Refer to profile.xls
	compressed_distance	N	UINT16	Accumulated distance
	compressed_cycles	N	UINT16	Accumulated cycles
	compressed_active_time	N	UINT16	Accumulated active time

As indicated in the “Required” column, not all of the listed fields shall be included in the Activity file. At a minimum, the following is required:

- file_id message must be included to indicate the file type, file_number, product information and time created. File_number is used to determine the type of data contained in the monitoring file (refer section 15.1.1).
- monitoring message containing timestamp and at least one of the following fields: calories, distance, cycles, active_time, activity_type, activity_level , compressed_distance, compressed_cycles, compressed_active_time

- If monitoring_info message is used, both timestamp and local_timestamp shall be included.

The activity_type, activity_subtype and activity_level fields are used to classify the recorded data. These fields are optional.

The monitoring_info message is optional. This message allows a local time zone offset to be established.

15.1.1 Monitoring File Definitions

The file_id.file_number field is used to describe the data contained in the monitoring file as described in Table 15-2.

Table 15-2. FIT Monitoring File file_id.file_number Format

FIT Field	Bits	Description	Value/Units
file_id.file_number	6:15	File_subtype	0: Generic Monitoring File
			1: activity monitoring data
			2:1023 - Reserved
	0:5	File_duration	0: Generic/All data
			1: New Data (since last download or power up)
			2: Detailed Daily (24 hours)
			3:63 - reserved

15.1.2 Accumulated Values

Monitoring data is logged in intervals and some fields are stored using accumulated values. This means that data for a specific logging interval is calculated from the *difference* between two timestamps. For example if data is logged hourly as shown below:

- **Record1:** Timestamp = Monday 15 August 2011 8:00am; cycles = 200; activity_type = walking
- **Record2:** Timestamp = Monday 15 August 2011 9:00am; cycles = 1200; activity_type = walking

These two records correspond to a single 1 hour logging interval. The number of steps taken in that logging interval is simply calculated as:

- Record2 – Record1 = 1000 walking steps


Monitoring files that use accumulated values, shall always log a starting point. The starting point shall be zero, or the last known recorded value.

Refer to sections 15.2 and 15.3 for more detailed examples.


15.2 Monitoring File Example

The FIT monitoring file includes the file_id, monitoring and optional messages (e.g. monitoring_info, device_info). These messages are structured as shown in Figure 15-2.


file_id message:



monitoring_info message:



monitoring message:



device_info message:




Figure 15-2. FIT Monitoring File Messages & Fields

Data from multiple activity types may be linked by timestamp. Figure 15-3 shows example data from an activity monitor that records running, cycling and 'generic' activity. Data is logged hourly for each activity type.

	timestamp	activity_type	calories	distance	# cycles	active_time	
h	Monday 9:00am	2	0	0	0	0	cycling
h	Monday 9:00am	1	0	0	0	0	running
h	Monday 9:00am	0	0	0	0	0	generic
h	Monday 10:00am	2	120	3000	2700	30mins	cycling
h	Monday 10:00am	1	150	1500	2400	30mins	running
h	Monday 10:00am	0	0	0	0	0	generic
h	Monday 11:00am	2	240	6000	5400	60mins	cycling
h	Monday 11:00am	1	300	3000	4800	60mins	running
h	Monday 11:00am	0	0	0	0	0	generic
↑			⋮				

(h: normal header, local message type = 0)

Figure 15-3. Example FIT Monitoring File Data Records

In this example, the following data may be calculated:

- Between 9 am and 10 am:
 - Cycling: 120 calories, 3 km, and 2700 "cycles" occurred over 30 minutes.
 - Running: 150 calories, 1.5 km, and 2400 steps occurred over 30 minutes.
 - No generic activity was recorded
- Between 10 am and 11 am:
 - Cycling: 120 calories, 3 km, and 2700 "cycles" occurred over 30 minutes.
 - Running: 150 calories, 1.5 km, and 2400 steps occurred over 30 minutes.
 - No generic activity was recorded

15.3 File Optimisation Options

File optimisation techniques may be used to further reduce the FIT monitoring file size. These optional optimisation techniques are discussed in the following sections.

15.3.1 Compressed Timestamp Headers

For activity monitors that detect more than one activity type, multiple data messages may be recorded for a single timestamp value (as shown in earlier example of Figure 15-3). In this case, the sport and/or activity_level field shall be included to differentiate the activities, and data for the same logging interval is linked using identical timestamps.

Compressed timestamp headers may be used to reduce file size by eliminating the need of a four byte timestamp for *every* data record. Instead, a single 4 byte timestamp may be used for the first data message of a specific point in time, using a normal record header, and compressed timestamp headers may be used for identically timestamped data of different activity types. Refer to Figure 15-4 for an example.




Figure 15-4. Example FIT Monitoring File Data Records with Compressed Timestamp Headers

In the given example, activity_type = 0 indicates generic activity, activity_type = 1 is running, and activity_type = 2 indicates cycling. Each activity type is recorded at a 1 hr logging interval.

The timestamp fields can be used to link records. The header byte indicates if the FIT message is recorded using a normal header (h0), or a compressed timestamp header (h1).

Using a compressed timestamp header (h1) will allow linked data to be recorded without a 4 byte timestamp; instead, the header includes a time offset from the last recorded timestamp. In this case, the first record uses a normal header (h0) and sets the time at Monday 9:00am. The two subsequent compressed timestamp headers (h1) indicate an offset of 0 seconds. This links the first 3 messages at Monday 9:00am.

Similarly, the next record uses a normal header (h0) and sets the time at Monday 10:00am, and the two subsequent compressed timestamp headers (h1) indicate an offset of 0 seconds, linking the next 3 messages at Monday 10:00am.

Note, compressed time headers are only used/necessary if multiple activity_types, activity_subtypes or activity_levels are recorded.

If using compressed timestamp headers, two local message types will be required:

- one local message type defined to include the timestamp field, and used with a normal record header. The data message will serve as the time reference for linked records (h0 in the example).
- one local message type shall be defined not including the timestamp field and used with the time compressed header showing 0 seconds offset (h1 in the example).

Calories, cycles, distance, and active time are accumulated values. This means that the actual values for a set logging interval are calculated as the difference between the current and previous records. **As a result, a starting point shall always be logged.** The starting point shall be zero, or the last known recorded value.

In the provided example, there are two intervals recorded. The starting point is a zero point and activity data is calculated for each activity_type and logging interval as shown below:

1st logging interval (9-10am):

- no generic activity
- 30 mins of running, 150 cals, 1.5km, 2400 steps
- 30 mins of cycling, 120 cals, 3km, 2700 cycles

2nd logging interval (10-11am):

- no generic activity
- 30 mins of running, 150 cals, 1.5km, 2400 steps
- 30 mins of cycling, 120 cals, 3km, 2700 cycles

15.3.2 Data Record Compression

Unchanging monitoring data does not have to be logged for each time logging interval. In the example in Figure 15-4, the activity monitor did not record any “generic” activity between 9 and 11 am. The file could further be compressed by omitting the “generic” monitoring messages until actual “generic” activity data is recorded for that activity type (Figure 15-5).




Figure 15-5. Example 1: Compressed Timestamp Headers & Data Record Compression

It is possible using this method that some time resolution may be lost; in Figure 15-5, for example, 40 minutes and 30 seconds of generic activity was recorded sometime between 9:00am and 5:00pm, but it's not known exactly when in that 8 hours the activity occurred.

16 Daily Monitoring File

Daily monitoring files follow the same format as monitoring files, however data is logged at a 24 hour time intervals (Figure 16-1). This allows summary information to be stored separately in a small file for rapid download. The FIT **file_id.type = 28 (0x1C)** for a daily monitoring file.




Figure 16-1. Daily Monitoring File

Daily monitoring files follow the same requirements as for a monitoring file:

- The same required fields as stated in Table 15-1.
- The same file structure.
- The same file optimization and compression techniques.

Different requirements:

- The data shall be recorded at a logging_interval of 24 hours (i.e. daily values).
- The file_id.file_number structure is similar as for a monitoring file, however, the file_duration field is as defined in Table 16-1.

Table 16-1. FIT Daily Monitoring File file_id.file_number Format

FIT Field	Bits	Description	Value/Units
file_id.file_number	6:15	File_subtype	0: Generic Monitoring File
			1: activity monitoring data
			2:1023 - Reserved
	0:5	File_duration	0: Generic/All data
			1: New Data (since last download or power up)
			2: monthly
			3:63 - reserved